

Removal of Zona Pellucida with Pronase in Cattle

Luiz Augusto de Castro e Paula, C. Moises Franco, and Peter J. Hansen

Dept. of Animal Sciences, University of Florida

Materials

Phoshpate buffered saline (PBS) - one can use either Dulbecco's PBS for ease of preparation, 10 mM KPO₄, pH 7.4 containing 0.154 M NaCl or the same buffer with NaPO₄.

8% (w/v) paraformaldehyde stock solution: Dissolve 8 g of powdered paraformaldehyde in 100 ml water. Heat and stir (55-60°C – do not go higher). Add a few drops of 2 N sodium hydroxide until the solution clears. Make fresh each day. Alternatively, 8% paraformaldehyde can be purchased from Electron Microscopy Sciences as a custom formulation in 4 ml aliquots (cat. no. 15710-SP). Throw away whatever is not used in one day.

4% (v/v) paraformaldehyde: 1:1 solution of 8% paraformaldehyde stock solution and PBS. Make up on the day of use.

Protease (0.1%, w/v) - weigh 0.1 g protease, add to a volumetric flask and add 100 ml of PBS (0.1 M). Aliquot in 1 ml tubes and store at -20°C until use.

Protocol

- 1) Remove the embryos from the culture drop and wash them at least 3 times in PBS containing 1 mg/ml polyvinylpyrrolidone (PBS-PVP).
- 2) Put the embryos (as few as possible at each time) in a 50 μ l drop of 0.1% protease and immediately watching them using a high magnification microscope that allows you to see the zona clearly. Leave the embryos in the drop until the zona is removed (up to 1 5 minutes). BE CAREFUL!!! Otherwise the protease will digest the embryo too!!!!!! Differences between stages of development from oocyte to expanded blastocyst may affect the time necessary for protease action.
- 3) Wash embryos very quickly 3 times in PBS-PVP and place them in a 50 μ l drop of paraformaldehyde solution [4% (w/v) in PBS]. The digestion seems to stop only when the embryos are in the paraformaldehyde drop (so be fast!!!).
- 4) Keep embryos in the paraformaldehyde drop for 1 h at room temperature for fixation.
- 5) Wash the embryos 3 times in a 50 μ l drop PBS/ PVP by transferring the embryos from drop to drop (2 min for each wash).
- 6) Store the embryos at 4 °C in 4-well plates until further use in other procedures.

Created 7-24-2007; modified 8-12-2011